

Scale Ticket Level Management - Correcting Transferred Tickets

Last Modified on 04/02/2025 9:59 am CDT

In Grain, there are two models of operation:

- The Standard model where Scale Tickets are directly associated to the Assembly
- Scale Ticket Level Management where Scale Tickets have an independent relationship to the Assembly.

Setup for these two models is inherently different and therefore not interchangeable within Grain.

The information in this article is specific to the Scale Ticket Level Management model.

When a new STLM Scale Ticket is saved, it is transferred to Grain, updating the DPR and contracts. If an error is discovered, it can be corrected by editing a Scale Ticket at *Grain / Advance Grain Scale Interface / Operations / Scale Ticket*.

If a Scale Ticket has been transferred to Grain and not *Posted*, the **Correct** button is available.

<Name>	Share%	Contract	DPR	Action	Hold
1 Barry...	100.00...			Imp	

Test	Result
1 TW	
2 M...	
3 D...	
4 FM	

Ticket #	Location	Commodity	Cust Ref	Customer Name	Direction	Vehicle	GF1	GF2
200008	02MISO	Corn	AndBa	Barry Anderson	In			

Impacts of the Correct Button

Using the **Correct** button immediately deletes the ticket in Grain, updates the DPR and contract and marks the

Scale Ticket as not printed and not transferred. The ticket number is deleted, and counting continues without skipping or duplicating a number.

Correcting the Data

Highlight the ticket and select **Correct** to display the *Edit a Grain Scale Ticket* window. Make necessary corrections to the ticket and select **Save** to transfer the Scale Ticket into Grain.

The screenshot shows the 'Edit a Scale Ticket (Scale 1)' window. It includes fields for Assembly, Location (02MISO), Commodity (Corn), Ticket # (200008), Ticket Date (04/02/20), Cash Price (0.0000), Gross Weight (55000 lb), Tare Weight (12000 lb), Net Weight (43000 lb), Dockage % (0), Shrink % (0), Gross Units (767.86), Dock Units (0.00), Shrink Units (0.00), Total Dock (0.00), and Net Units (767.86). There are also buttons for 'Start' and 'Stop'. A table shows test results with columns 'Test' and 'Result'. A list of tickets is shown at the bottom, with the selected ticket highlighted. The 'Save' button is highlighted with a red box.

Ticket #	Location	Commodity	Cust Ref	Customer Name	Direction	Vehicle	GF1	GF2
200005	02MISO	Corn	238022	Russ Felger	In			
200006	02MISO	Corn	238022	Russ Felger	In			
200007	02MISO	Corn	238022	Russ Felger	In			
200008	02MISO	Corn	AndBa	Barry Anderson	In			

Delete Scale Ticket

If a Scale Ticket is *Posted* in Grain or, if a ticket is in process (designated by an asterisk), the **Correct** button will not display. The **Delete** button allows removal of the ticket and the ability to start over.

Edit a Scale Ticket

<Assembly #> 8001

<Location> 02MISO <Commodity> Corn <Variety>

Ticket # 9500 Date

Ticket Prefix Suffix

Base Price 0.0000 <Farm ID>

Gross Weight 54000 <Field ID> Lot Num

Tare Weight 12000

Net Weight 42000

Gross Units 750.00

Dock Units 0.00

Shrink Units 0.00

Total S/D Units 0.00

Net Units 750.00

Variety

<Comment>

<Freight Vendor>

	Test	Result	Prem/Disc	<Premium Schedule>
1	TW			NOSCHEDULE
2	M...			NOSCHEDULE
3	D...			NOSCHEDULE
4	FM			NOSCHEDULE
5	Sour			NOSCHEDULE
6	M...			NOSCHEDULE
7	HD			NOSCHEDULE

Total Prem/Disc 0.0000

<Bin> ?

BL/Car #

Edit a Scale Ticket (Scale 1)

<Assembly #>

<Location> 02MISO <Commodity> Corn <Variety>

Ticket # 200007

Ticket Date

Cash Price 0.0000

Gross Weight 45555 lb

Tare Weight lb

Net Weight 45555 lb

Dockage % 0

Shrink % 0

Gross Units 0.00

Dock Units 0.00

Shrink Units 0.00

Total Dock 0.00

Net Units 0.00

	<Name>	Share%	Contract	DPR	Action	Hold
1	Russ F...	100.00...		O	Imp	<input type="checkbox"/>

<Farm ID> <Field ID>

	Test	Result
1	TW	
2	M...	
3	D...	
4	FM	

<Comment>

<Bin> BL/Car # Vehicle BOL Info

Pit ID <Freight Vendor>

IN - 1 Inbound Outbound Type Scale Ticket

Enable Tester <Weighmaster>

Ready For Transfer Axles 0

Auto Refresh Sec 60 Filter List Direction All

Ticket #	Location	Commodity	Cust Ref	Customer Name	Direction	Vehicle	GF1	GF2
9497	02MISO	Corn	238022	Russ Felger	In			
9500	02MISO	Corn	238022	Russ Felger	In			
9501	02MISO	Corn	238022	Russ Felger	* In			

User Security for Access to the Correct and Delete Buttons

Allowing use of the **Correct** or **Delete** button can be designated on the User Role by selecting **Roles at Hub / Setup /**

Users and navigating to the *Window Restrictions* tab.